

# NAG C Library Function Document

## nag\_opt\_read (e04xyc)

### 1 Purpose

nag\_opt\_read (e04xyc) reads a set of optional parameter values from a file and assigns those values to a given options structure of type **Nag\_E04\_Opt**. Values supplied are checked as being of correct type for the specified optional parameter.

### 2 Specification

```
#include <nag.h>
#include <nage04.h>

void nag_opt_read(char *name, char *opt_file, Nag_E04_Opt *options,
                  Boolean print, char *outfile, NagError *fail)
```

### 3 Description

The optimization functions of Chapter e04 have a number of optional parameters, which are set by means of a structure of type **Nag\_E04\_Opt**. Optional parameter values may be assigned to members of the options structure directly in the program text and/or by supplying the optional values in a file which can be read by the function nag\_opt\_read.

When optional parameter values are read from a file using nag\_opt\_read then the options structure will be initialized automatically if this has not already been done. It is only necessary to call nag\_opt\_init (e04xxc) if direct assignments to the options structure are made in the user's program before calling nag\_opt\_read.

As well as reading from a file, nag\_opt\_read will also read from `stdin`. This allows redirection to be used to supply the file; it also permits nag\_opt\_read to be used interactively with the user supplying values from the keyboard.

Checks are made that the values read in are of valid type for the optional parameter specified and (except for nag\_opt\_nlp\_sparse (e04ugc)) that the value is within the range for that parameter. If a value is accepted, a printed confirmation of the setting of the relevant parameter will be output if `print = TRUE`. An unacceptable parameter name or value will give an error message if `fail.print = TRUE`.

### 4 Parameters

1: **name** – `char *`

*Input*

*On entry:* a character string specifying either the NAG six character name or the NAG long name of the proposed optimization routine. The case of the character string is disregarded.

2: **opt\_file** – `char *`

*Input*

*On entry:* the name of the file which specifies the optional parameter values. If `stdin` is to be used, the string "stdin" should be supplied. The set of option values must be preceded by the keyword `begin` followed by the function name for which the set of options is being supplied. The function name may be the six character NAG name of an optimization routine or its associated long name.

Each option value specified in the file must be preceded by the name of the optional parameter. The parameter name and value must be separated by at least one blank space or an equals symbol. nag\_opt\_read will read to the end of file or until the keyword `end` is found or until another `begin` is found. C style comments may be placed within a set of option values to aid the user's documentation. Outside the option value sets, text need not be within C style comment delimiters.

**Note:** assignment to function pointers in the options structure, memory allocation to array pointers and assignment of trailing array dimensions cannot be performed from an options file. These must be assigned directly to the options structure in the user's calling program.

3: **options** – Nag\_E04\_Opt \*

*On entry:* the options structure may or may not have previously been initialized, and had values assigned to its members.

*On exit:* the options structure, initialized and with values assigned according to the values found in the options file.

4: **print** – Boolean

*Input*

*On entry:* if **TRUE** a message confirming the setting of each option will be output.

5: **outfile** – char \*

*Input*

*On entry:* a character string specifying the name of the file to which confirmation messages should be output. If **stdout** is required then the string "stdout" should be given. When **print** = **FALSE** the empty string "" can be supplied as **outfile** will be ignored.

6: **fail** – NagError \*

*Input/Output*

The NAG error parameter (see the Essential Introduction).

## 5 Error Indicators and Warnings

### NE\_INVALID\_BEGIN

The Begin statement occurring in data file from which options are being read is not valid.

### NE\_NOT\_FUN\_NAME

The string, *<string>*, supplied in the parameter name is not the name of any C Library function with option setting facilities.

### NE\_INVALID\_OPTION\_NAME

(line *<value>*) '*<string>*' is not a valid name for a structure member or option.

This error message is output if, for example, the specified string contains characters which are not permitted in a variable name in the C programming language.

### NE\_INVALID\_OPTION

(line *<value>*) *<string>* cannot be assigned to using an options file.

### NE\_FIELD\_UNKNOWN

(line *<value>*) '*<string>*' is not a permitted structure member or option for *<string>*.

### NE\_INVALID\_VALUE

(line *<value>*) is not a permitted structure member or option for *<string>*.

### NE\_NO\_VALUE

(line *<value>*) no value found for option *<string>*.

### NE\_UNBALANCED\_COMMENT

Unbalanced comment starting on line *<value>* found in options file.

### NE\_INVALID\_INT\_RANGE\_1

### NE\_INVALID\_REAL\_RANGE\_E

### NE\_INVALID\_REAL\_RANGE\_F

Value *<value>* given to *<option>* is not valid. Correct range is *<option>* *<value>*.

**NE\_INVALID\_INT\_RANGE\_2**  
**NE\_INVALID\_REAL\_RANGE\_EF**  
**NE\_INVALID\_REAL\_RANGE\_FF**

Value  $\langle value \rangle$  given to  $\langle option \rangle$  is not valid. Correct range is  $\langle value \rangle \langle option \rangle \langle value \rangle$ .

**NE\_INVALID\_REAL\_RANGE\_CONS**

Value  $\langle value \rangle$  given to  $\langle option \rangle$  not valid. The parameter  $\langle option \rangle$  must satisfy  $\langle constraint \rangle$ .

**NE\_INVALID\_TEXT\_RANGE**

Value  $\langle string \rangle$  given to  $\langle option \rangle$  not valid.

**NE\_INVALID\_ENUM\_RANGE**

Enum value  $\langle string \rangle$  given to  $\langle option \rangle$  is not valid for this function.

**NE\_NOT\_READ\_FILE**

Cannot open file  $\langle string \rangle$  for reading.

**NE\_NOT\_APPEND\_FILE**

Cannot open file  $\langle string \rangle$  for appending.

**NE\_NOT\_CLOSE\_FILE**

Cannot close file  $\langle string \rangle$ .

**NE\_WRITE\_ERROR**

Error occurred when writing to file  $\langle string \rangle$ .

The following error messages are specific to option setting for nag\_opt\_conj\_grad (e04dgc), nag\_opt\_nlp (e04ucc) and nag\_opt\_nlin\_lsq (e04unc).

**NE\_STOP\_LT\_START**

Value given to obj\_check\_stop,  $\langle value \rangle$ , is less than value given to obj\_check\_start,  $\langle value \rangle$ .

**NE\_CHECK\_LT\_ONE**

Value  $\langle value \rangle$  given to  $\langle string \rangle$  is less than 1.

## 6 Further Comments

nag\_opt\_read may be used to read the optional ‘MPSX names’ (e.g., **prob\_name**, **obj\_name**) for nag\_opt\_sparse\_mps\_read (e04mzc) and nag\_opt\_sparse\_convex\_qp (e04nkc). However, although these functions allow the names to contain non-leading blank characters, nag\_opt\_read will not read such names correctly from an options file since blank spaces are assumed to denote the end of an option name or value within the file. All other valid MPSX names (see the documentation for nag\_opt\_sparse\_mps\_read (e04mzc) for details) will be read correctly by nag\_opt\_read.

## 7 See Also

nag\_opt\_sparse\_mps\_read (e04mzc)

nag\_opt\_init (e04xxc)

nag\_opt\_free (e04xzc)

the e04 Chapter Introduction

## 8 Example

See the use of nag\_opt\_read (e04xyc) in any of the example programs for nag\_opt\_simplex (e04ccc), nag\_opt\_conj\_grad (e04dgc), nag\_opt\_lsq\_no\_deriv (e04fcc), nag\_opt\_lsq\_deriv (e04gbc), nag\_opt\_bounds\_no\_deriv (e04jbc), nag\_opt\_bounds\_deriv (e04kbc), nag\_opt\_bounds\_2nd\_deriv (e04lbc), nag\_opt\_lp (e04mfc), nag\_opt\_qp (e04nfc), nag\_opt\_nlp (e04ucc) and nag\_opt\_nlp\_sparse (e04ugc).

---