E01RBF – NAG Fortran Library Routine Document

Note. Before using this routine, please read the Users' Note for your implementation to check the interpretation of bold italicised terms and other implementation-dependent details.

1 Purpose

E01RBF evaluates continued fractions of the form produced by E01RAF.

2 Specification

SUBROUTINE E01RBF(M, A, U, X, F, IFAIL)INTEGERM, IFAILrealA(M), U(M), X, F

3 Description

E01RBF evaluates the continued fraction

$$R(x) = a_1 + R_m(x)$$

where

$$R_i(x) = \frac{a_{m-i+2}(x - u_{m-i+1})}{1 + R_{i-1}(x)}, \quad \text{for } i = m, m-1, \dots, 2.$$

and

 $R_1(x) = 0$

for a prescribed value of x. E01RBF is intended to be used to evaluate the continued fraction representation (of an interpolatory rational function) produced by E01RAF.

4 References

 Graves-Morris P R and Hopkins T R (1981) Reliable rational interpolation Numer. Math. 36 111–128

5 Parameters

1: M — INTEGER

On entry: m, the number of terms in the continued fraction.

Constraint: $M \ge 1$.

2: A(M) - real array

On entry: A(j) must be set to the value of the parameter a_j in the continued fraction, for j = 1, 2, ..., m.

3: U(M) - real array

On entry: U(j) must be set to the value of the parameter u_j in the continued fraction, for j = 1, 2, ..., m - 1. (The element U(m) is not used).

On entry: the value of x at which the continued fraction is to be evaluated.

5:
$$F - real$$

Output
On exit: the value of the continued fraction corresponding to the value of x.

[NP3390/19/pdf]

Input

Input

Input

6: IFAIL — INTEGER

Input/Output

On entry: IFAIL must be set to 0, -1 or 1. For users not familiar with this parameter (described in Chapter P01) the recommended value is 0.

On exit: IFAIL = 0 unless the routine detects an error (see Section 6).

6 Error Indicators and Warnings

Errors detected by the routine:

IFAIL = 1

The value of X corresponds to a pole of R(x) or is so close that an overflow is likely to ensue.

7 Accuracy

See Section 7 of the document for E01RAF.

8 Further Comments

The time taken by the routine is approximately proportional to m.

9 Example

This example program reads in the parameters a_j and u_j of a continued fraction (as determined by the example for E01RAF) and evaluates the continued fraction at a point x.

9.1 Program Text

Note. The listing of the example program presented below uses bold italicised terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```
E01RBF Example Program Text
*
*
     Mark 14 Revised. NAG Copyright 1989.
      .. Parameters ..
*
      INTEGER
                       М
     PARAMETER
                       (M=4)
                       NIN, NOUT
      INTEGER
     PARAMETER
                       (NIN=5,NOUT=6)
      .. Local Scalars ..
     real
                       F, X
      INTEGER
                       I, IFAIL
      .. Local Arrays ..
     real
                       A(M), U(M)
      .. External Subroutines ..
     EXTERNAL
                       E01RBF
      .. Executable Statements ..
      WRITE (NOUT,*) 'E01RBF Example Program Results'
     Skip heading in data file
     READ (NIN,*)
     READ (NIN,*) (A(I),I=1,M)
     READ (NIN,*) (U(I),I=1,M-1)
     READ (NIN,*) X
      WRITE (NOUT,*)
     WRITE (NOUT,99999) 'X =', X
      IFAIL = 0
```

*

```
CALL E01RBF(M,A,U,X,F,IFAIL)
*
WRITE (NOUT,*)
WRITE (NOUT,99999) 'The value of R(X) is ', F
STOP
*
99999 FORMAT (1X,A,1P,e12.4)
END
```

9.2 Program Data

```
E01RBF Example Program Data
4.000 1.000 0.750 -1.000
0.000 3.000 1.000
6.000
```

9.3 Program Results

E01RBF Example Program Results

X = 6.0000E+00

The value of R(X) is 1.7714E+01