X04DEF - NAG Fortran Library Routine Document

Note. Before using this routine, please read the Users' Note for your implementation to check the interpretation of bold italicised terms and other implementation-dependent details.

1 Purpose

X04DEF is an easy-to-use routine to print a *complex* band matrix stored in a packed two-dimensional array.

2 Specification

```
SUBROUTINE XO4DEF(M, N, KL, KU, A, LDA, TITLE, IFAIL)
```

INTEGER M, N, KL, KU, LDA, IFAIL

complex A (LDA,*) CHARACTER*(*) TITLE

3 Description

X04DEF prints a *complex* band matrix stored in a packed two-dimensional array. It is an easy-to-use driver for X04DFF. The routine uses default values for the format in which numbers are printed, for labelling the rows and columns, and for output record length.

X04DEF will choose a format code such that numbers will be printed with either an F8.4, F11.4 or a 1PE13.4 format. The F8.4 code is chosen if the sizes of all the matrix elements to be printed lie between 0.001 and 1.0. The F11.4 code is chosen if the sizes of all the matrix elements to be printed lie between 0.001 and 9999.9999. Otherwise the 1PE13.4 code is chosen. The chosen code is used to print each complex element of the matrix with the real part above the imaginary part.

The matrix is printed with integer row and column labels, and with a maximum record length of 80.

The matrix is output to the unit defined by X04ABF.

4 References

None.

5 Parameters

1: M — INTEGER

2: N — INTEGER Input

On entry: the number of rows and columns of the band matrix, respectively, to be printed.

If either of M or N is less than 1, X04DEF will exit immediately after printing TITLE; no row or column labels are printed.

3: KL — INTEGER Input

On entry: the number of sub-diagonals of the band matrix A.

Constraint: $KL \geq 0$.

4: KU — INTEGER Input

On entry: the number of super-diagonals of the band matrix A.

Constraint: $KU \ge 0$.

[NP3390/19/pdf] X04DEF.1

5: A(LDA,*) - complex array

Input

Note: the second dimension of the array A must be at least max(1,min(M+KU,N)).

On entry: the band matrix to be printed. The leading (KL + KU + 1) by min(M + KU, N) part of array A must contain the matrix, packed column by column, with the leading diagonal of the matrix in row (KU + 1) of the array, the first super-diagonal starting at position 2 in row KU, the first sub-diagonal starting at position 1 in row (KU + 2), and so on. Elements in the array A that do not correspond to elements in the band matrix (such as the top left KU by KU triangle) are not referenced, and need not be set.

6: LDA — INTEGER

Input

On entry: the first dimension of the array A as declared in the (sub)program from which X04DEF is called.

Constraint: LDA > KL + KU + 1.

7: TITLE — CHARACTER*(*)

Input

On entry: a title to be printed above the matrix. If TITLE = '', no title (and no blank line) will be printed.

If TITLE contains more than 80 characters, the contents of TITLE will be wrapped onto more than one line, with the break after 80 characters.

Any trailing blank characters in TITLE are ignored.

8: IFAIL — INTEGER

Input/Output

On entry: IFAIL must be set to 0, -1 or 1. For users not familiar with this parameter (described in Chapter P01) the recommended value is 0.

On exit: IFAIL = 0 unless the routine detects an error (see Section 6).

6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors detected by the routine:

IFAIL = 1

On entry, KL < 0.

IFAIL = 2

On entry, KU < 0.

IFAIL = 3

On entry, LDA < KL + KU + 1.

7 Accuracy

Not applicable.

X04DEF.2 [NP3390/19/pdf]

8 Further Comments

A call to X04DFF is equivalent to a call to X04DFF with the following argument values:

```
NCOLS = 80
INDENT = 0
LABROW = 'I'
LABCOL = 'I'
FORMAT = '''
USEFRM = 'A'
```

9 Example

This example program calls X04DEF to print a 5 by 5 band matrix with one sub-diagonal and one super-diagonal.

9.1 Program Text

Note. The listing of the example program presented below uses bold italicised terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```
XO4DEF Example Program Text
  Mark 14 Release. NAG Copyright 1989.
   .. Parameters ..
   INTEGER
                    NOUT
  PARAMETER
                    (NOUT=6)
   INTEGER
                    NMAX, LDA
  PARAMETER
                    (NMAX=5,LDA=NMAX)
   .. Local Scalars ..
  real
   INTEGER
                    I, IFAIL, J
   .. Local Arrays ..
  complex
                    A(LDA, NMAX)
   .. External Subroutines ..
  EXTERNAL
                    X04DEF
   .. Intrinsic Functions ..
   INTRINSIC
                    cmplx
   .. Executable Statements ...
   WRITE (NOUT,*) 'XO4DEF Example Program Results'
  WRITE (NOUT,*)
  Generate an array of data
  DO 40 J = 1, NMAX
      DO 20 I = 1, LDA
         AA = 10*I + J
         A(I,J) = cmplx(AA,-AA)
20
      CONTINUE
40 CONTINUE
   IFAIL = 0
  Print 5 by 5 band matrix with 1 sub-diagonal and 1 super-diagonal
   CALL XO4DEF(5,5,1,1,A,LDA,'Band Matrix:',IFAIL)
  STOP
  END
```

[NP3390/19/pdf] X04DEF.3

9.2 Program Data

None.

9.3 Program Results

XO4DEF Example Program Results

| Band Matrix: | | | | | |
|--------------|----------|----------|----------|----------|----------|
| | 1 | 2 | 3 | 4 | 5 |
| 1 | 21.0000 | 12.0000 | | | |
| | -21.0000 | -12.0000 | | | |
| 2 | 31.0000 | 22.0000 | 13.0000 | | |
| | -31.0000 | -22.0000 | -13.0000 | | |
| 3 | | 32.0000 | 23.0000 | 14.0000 | |
| | | -32.0000 | -23.0000 | -14.0000 | |
| 4 | | | 33.0000 | 24.0000 | 15.0000 |
| | | | -33.0000 | -24.0000 | -15.0000 |
| 5 | | | | 34.0000 | 25.0000 |
| | | | | -34.0000 | -25.0000 |
| | | | | | |

X04DEF.4 (last) [NP3390/19/pdf]